



Installation Guide – Nahimic App and Drivers

Document Name	Installation Guide – Nahimic App and Drivers
Document Version	1.1
Document Creation Date	
Document Modification Date	July 18, 2022
Document Author	Danny Lee
Document Validation	

Contents

I. Revision History	2
II. Introductions.....	2
III. Installing drivers using once click installer.	3
IV. Manually installing the drivers.....	3
V. Installing the Nahimic 3 app.....	4
VI. Note	5

I. Revision History

Revision	Date (DD/MM/YYYY)	Description	Author	Approval
1.0	7 June 2021		Sean Goh	
1.1	18 July 2022		Danny Lee	


II. Introductions

This document explains how to install Nahimic 3 from the driver installation to the APPX installation.

Please follow this tutorial and use the provided Nahimic Package.

This package contains 2 folders which represent the 2 phases of the install process:


1. Driver: contains Nahimic Driver and APO components
2. Nahimic3: Contains Nahimic3 APPX



III. Installing drivers using once click installer.

1. Open “1 – Drivers’ Folder, you will see all the necessary drivers that need to be installed as well as a Restoretool exe which is the one click installer for the drivers:

2. Run the Restoretool as Administrator



3. Follow any instructions the tool might prompt to install the drivers

4. Restart the computer once installation is completed


IV. Manually installing the drivers

1. Open “1 – Drivers’ Folder, you will see all the necessary drivers that need to be installed as well as a Restoretool exe which is the one click installer for the drivers:

2. Go into each driver’s folder and locate the .inf System Information file

3. Right click on the .inf file and click on Install

e.g.




4. Repeat step 2 & 3 for all the drivers in the “1 – Drivers” folder

5. Restart the computer once all the drivers have been installed.


V. Installing the Nahimic 3 app

NOTE: Make sure that the drivers are installed first before you install the app.

1. Open “2 – Nahimic 3” folder, you will see a zip file of the preinstall package for the app



2. Unzip the preinstall package and locate the APPXBUNDLE file



3. Double click the APPXBUNDLE file, and follow the instructions that show up to install the app

4. Restart the computer once installation is completed.

VI. Note

1. Drivers do not have to be installed in any particular order, but we would recommend installing the Ext-INF driver first before everything else
2. The Nahimic solution only works on machines that are listed in our supported HWID list. The HWID of the machines Realtek Audio device needs to correspond to any of the HWIDs in our supported list for the solution to be able to work.
3. Nahimic 3 App's version number can be found in the Nahimic 3 UI under the Settings Tab
4. The drivers version numbers can be found from their Device properties under the Device Manager. You can also use tools to check for the version number as well.